


Sending HCPC Recipes to Hobart Combi

Screenshot Instructions (Windows 7 PC that has Bluetooth)


1. Activate Bluetooth
 - a. Click on arrow
 - b. Click on Bluetooth device and turn on
 - c. Click on "Add a Device"




2. Add a Device




3. Select the combi device indicated by the device starting with "F000.....". Each combi will have a unique version of this alphanumeric code but they will all start the same first letter and numbers.




4. Enter the pairing code "0000".




5. Adding a device is now complete.




6. Right click on the newly added device and press "Control".




7. Click on "Send files" to device.



8. Click on "Browse Files" and then locate correct file in C: Drive, Program Files, HCPC98, PROG. The recipe file to upload to the combi will always be a .jpg file with the same image icon shown below. HCPC ran as administrator will be in file location above (if not use "program files (x86)").



9. Press "Send" once correct HCPC recipe file is located.



10. Sending File is complete when combi sounds a long single beep. Recipes will now be in the combi.

